

All right! Here's the recipe for fermented sourdough bread!

Makes 2 loaves

FERMENTED SOURDOUGH BREAD

Ingredients

For the Levain:

- 25 grams bubbly sourdough starter
- 70 grams purified/spring water
- 70 grams organic all-purpose flour

Build the Dough:

- 725 + 50 grams purified/spring water
- 150 grams levain (see above)
- 200 grams organic whole wheat flour
- 800 grams organic all-purpose flour , divided
- 25 grams Celtic sea salt or Himalayan pink salt

Stretching, Folding and Bulk Fermentation:

- Organic white flour for dusting

For the Bake:

- About 60 grams rice flour for dusting bowls

Instructions

For the Levain:

1. The evening before you make bread, mix together 25 grams starter, 70 grams water and 70 grams flour in a 16oz mason jar or small bowl with straight sides. Mark the level with tape or a rubber band. Cover the mixture with a clean towel and leave on the counter at room temperature. The mixture will be ready in 10-12 hours and will double or even triple in volume.
2. Note: During hot months, this can take 6-8 hours depending on the temperature of your kitchen. You can use ice water to slow this process in the summer. Using water that is 130°F will speed this process into 4-5 hours, but for best flavor, I recommend allowing for a longer ferment time.

Build the Dough:

1. Pour 725 grams of water into a large glass or ceramic mixing bowl. Drop a tablespoon of levain into the bowl and see if it floats. If it floats, add the rest of the levain to the water and whisk to combine. If it doesn't float, wait another hour and try again. Add 200 grams of whole wheat flour and 300 grams of organic all-purpose flour to the water mixture and combine with a dough whisk . Add the remaining 500 grams of all-purpose flour and mix with your hands, making sure there are no dry clumps of flour.
2. Note: The temperature of your water in relation to your ambient room temperature is very important. In the wintertime, it's helpful to use warmer water and in the hottest months, ice water would be appropriate.
3. Cover and autolyse (let sit) for 30 minutes.
4. Add 25 grams Celtic sea salt or Himalayan salt and 50 grams of water and mix by hand until incorporated. Cover the dough with a clean cloth and let rest for 30 minutes.

Stretching, Folding and Bulk Fermentation:

1. Stretch and fold the dough four times (watch the video above and start at the 1:02 minute mark). Place a clean cloth over the dough and let it sit for 30 minutes. Then, stretch and fold the dough again, place a clean cloth over the dough and let sit for another 30 minutes. Repeat two more times for a total of four times.
2. During the second fold, herbs, olives, nuts, etc. can be added. Cover the dough with a clean cloth and allow it to rest for an hour.

3. Lightly dust a wooden board or a clean counter top with flour. Turn the dough out onto the floured surface. The dough will be sticky, so it helps to have wet hands. Using a bench knife or a large chef's knife, cut the dough in half and make two rounds of dough. Cover with a clean cloth and let sit for another hour.
4. Dust [two brotforms](#) with flour. If you don't have a brotform, you can use a basket lined with a dishtowel (if doing this, make sure the dust the dishtowel with flour). Don't skimp on the flour or your loaves will become difficult to remove when it's time to bake them.
5. Now it's time to shape the dough into a boule. You will do a series of four folds: bottom to top, top to bottom, left to right and right to left, before flipping over and shaping into a round. Then, gather the ball and place it upside down in a brotform (seam side up). (Watch [this video](#) and start at minute 1:16).

For the Final Rise:

1. Cover the dough loosely with a clean dish towel and allow to sit at room temp for another hour, then lightly tuck dish towel on top of the dough and place in refrigerator.
2. After the dough has been in the fridge for 12 hours (or the next morning), place each of the bowls with dough in a large plastic bag (I use [plastic bags that you can bake turkeys in](#)) to keep the dough from drying out and absorbing flavors from your refrigerator. After placing the loaves in the large plastic bags the loaves will remain in the fridge for another 24 hours for a total of 36-40 hours.

For the Bake:

1. Place a [Dutch Oven](#) with a lid in a cold oven. Preheat the oven to 500°F with your pot inside for one hour. Pull a loaf out from the refrigerator. Lightly dust the top (which is actually the bottom) with rice flour. Flip the loaf out onto a small cutting board. You can now score the top with a razor or lame, if desired. Carefully remove the hot pot from the oven, slide the loaf into the pot, place the lid back onto the pot and place in the oven. Be very careful. The pot is very hot!
2. Bake for 20 minutes. Carefully remove the lid (again, be careful because it's very hot), reduce the temperature to 465°F and bake for another 10-15 minutes until the bread is golden brown on top. You can also test for doneness with an instant read thermometer. If you put the thermometer in the middle of the loaf and it reads 190°-210°F then it's fully cooked.
3. Remove the loaf of bread from the pot and allow the bread to cool for at least one hour. The bread will continue baking during this time.
4. For your second loaf, you will return the pot to the hot oven and raise the temperature back up to 500° and let it heat up for 15 minutes before removing your second loaf from the refrigerator and repeating the process.
5. Note: Because all ovens vary, you will definitely want to purchase an [inexpensive oven thermometer](#) and place it in the back to make sure that your oven temperature is consistent and accurate.